

# Message Maker User's Guide

Message Maker Version 1.1

**DRAFT 1.1**

Robert Snelick

Len Gebase

Sydney Henrard

National Institute of Standards and Technology

rsnelick@nist.gov

## Preface


The Message Maker Project is a collaborative effort between the National Institute of Standards and Technology (NIST) and the Health Level 7 (HL7) Standards Consortium. NIST is directing its efforts towards the development of a conformance-testing tool that automatically generates test messages for HL7 message specifications. The messages can be used to test systems for conformance to a given profile. Message Maker is public domain software and is freely available. Message Maker is a work-in-progress, as such, not all planned functionality is implemented. This release is intended as a prototype; feedback on its design, feature set, and usefulness is welcomed.

This User's Guide provides an introduction on how to install and use the tool. This version gives an overview of key functionality. It is not yet a comprehensive guide. Please see Appendix A in this guide for a current list of known limitations of Message Maker.

## 1 Background

HL7 is an *application-level messaging standard* for the healthcare industry and defines the interfaces that allow centrally located and distributed information systems to communicate. HL7 establishes the rules for building interfaces and provides many optional features to accommodate the disparate needs of the health care industry. However, for interfaces to be implemented, a precise and unambiguous specification must be defined. Message profiles define processing rules and, by defining exactly which of the optional elements allowed by the standard that a message might include, provide an unambiguous XML description of HL7 messages. Tools, such as the Messaging Workbench (MWB), have been developed to help in the construction of message profiles. Interfaces modeled by a message profile need to be tested to ensure that they have been implemented correctly. Current practice involves meticulous by hand debugging of implementations as problems arise. Test message suites and the tools to create them are needed. Message Maker is one such tool that automatically generates test messages.

Message Maker dynamically constructs HL7 messages while parsing the message profile. Data values for the Field, Component, and SubComponent elements defined in the profile are obtained from a number of sources. The sources include the NIST developed database of HL7 data items, HL7 tables, user tables, external tables, and default values. Alternatively, data can be extracted from a site-specific database.



**Figure 1. Overview of Message Maker Process**

Message Maker creates a test suite of messages for a given profile. The messages can be valid or invalid and contain variation from message to message. An example of an invalid message is a missing data item for a required field. A number of test parameters can be varied in the construction of a message. These may include segment and field cardinality, the usage of certain primitive fields, value sets, data content, and more. Data content variation is achieved by randomly selecting items from the HL7 items database.

The core engine of Message Maker generates messages in XML. These messages can be subsequently transformed into the HL7 ER7 format. Figure 1 depicts a functional overview of Message Maker. Processing is XML based. Profile generation tools, such as MWB, export message specifications as XML documents. Data sources, converted into XML files, along with the profile are used by the XSL transformation generation engine to create the test messages. Metadata is recorded for each message. The metadata provides information on the purpose of the test messages. Later stages of this project will include a testing framework that will utilize these messages to examine the behavior of HL7 implementations.

## 2 Installation

### 2.1 Download

A copy of Message Maker can be obtained from the following website:

<http://www.nist.gov/messagemaker>

You can download either a self-installing executable jar or the entire software bundle that includes the source code. Choose the self-installing executable if you just plan on using the tool. The file name of the installer is *maker\_install\_n.n.jar*. Where *n.n* represents the version number.

### 2.2 System Requirements

Message Maker uses Java and XML technologies. The following software is required:

- Java 2 SDK (Version 1.4.2 or later)

Note that the self-installing executable is a jar file, so the Java 2 SDK needs to be installed in order to run it.


Message Maker has been tested on both Windows and Linux platforms. The following operating systems are supported:

- Windows XP
- Windows 2000
- Linux Redhat 9.0

Since Message Maker is Java based, it is likely that the software will run on other systems. However, the software has not been tested on other systems.

### 2.3 Installing Message Maker

Double-click on the installer's icon to run the self-installing executable to unpack and install the Message Maker software bundle. Then follow the instructions the installer provides—they are self-explanatory. Upon successful completion, you should see the run\_mm.bat (in the *maker bin* directory under your chosen install directory) and the

desktop short-cut icon  if you requested one. When done with the installation, you can delete the download file to recover disk space.

**Troubleshooting:** Installer won't execute.

The *installer* may not execute if the jar file does not have the proper file type association. One instance where this may occur is when you upgrade your java SDK version. First check to see that the *installer* is an *executable jar file* by examining its properties. If it is and still doesn't work, ensure that the proper execution instructions are associated with the file type. Below gives the steps for Windows 2000. Similar steps apply for other versions of Windows, including Windows XP.

In the *Window's File Explorer*, select the “**Folders Option ...**” item from the “**Tools**” menu. Then select the “**File Types**” tab. Check to see if there is a “*JAR*” extension with an “*Executable Jar File*” File Type in this list.

If it is not present:

- Select “**New**” and enter “*Jar*” for the file extension.
- Select the “**Advanced**” button and enter “*Executable Jar File*” in the text field at the top of the dialog
- Select “**New**”. Enter “*Open*” under Action: and enter “*C:\j2sdk1.4.2\_06\bin\javaw.exe -jar "%1" %\** (or the location of the *javaw* executable on your system) under “**Application used to perform action**”

- check the “**Use DDE**” box and enter the following in the text fields:

**DDE Message:**

**Application:** *javaw*

**DDE Application:**

**Topic:** *System*

If it is present:

- Confirm that it “Open withs” *javaw*. If not, select the **Change** button to launch the “**Open With**” dialog. Choose “**Other**” and navigate to the location of your Java installation (e.g., *C:\j2sdk1.4.2\_06\bin*) and then select “*javaw*”.
- Select “**Advanced**” and enter the string “*Executable Jar File*” in the text field at the top of the dialog.
- Under the “**Actions**” box, enter “*Open*” and make sure the “*Confirm open after download box*” is checked.
- Select “**Edit**” and enter the for these fields:

**Action:** *Open*

**Application used to perform action:** *C:\j2sdk1.4.2\_06\bin\javaw.exe -jar "%1" %\**

**Use DDE:** (confirm this box is checked)

**DDE Message:**

**Application:** *javaw*


**DDE Application:**

**Topic:** *System*

Note that in some cases it is easier to remove an existing Jar file type association and start with a new one.

## 2.4 Running Message Maker



To run Message Maker double-click on the  desktop short-cut icon or run the *run\_mm.bat* file in the directory where Message Maker was installed.

## 3 Overview of Message Creation

Below the basic steps to create messages for a given profile are listed. The user can specify the number of messages to generate and give Message Maker complete control

over the set of messages that are generated. Or, alternatively, the user can select specific options for controlling the types of messages that are generated.

### **Message Maker Process:**

**Initialization-** In this step the user selects the *Profile* which the messages will be based upon. A *session name* attaches a name to the current message generation setup. It can be used to later recall settings. The *message path* indicates the location where messages are to be stored.

**Setting Options-** The user can choose from a number of options when generating messages. By default Message Maker will create a set of valid message. The user can keep the default settings or customize the process. The *volume* parameter sets the number of messages that will be created.

**Data Initialization-** The user can set the values in the configuration file and the element database as needed. Values set in the configuration file become the default value for a particular data element. A typical element that might be set in the configuration file is the Sending Application (MSH-3.1). Also, values in the element database can be modified. Various utilities are provided by Message Maker to customize the data files.

**Message Generation-** After initialization is complete messages are generated automatically. Message Maker provides a utility that monitors the progress of the generation process. Messages are optionally validated against the profile to ensure correctness. A trace of the process is provided in a log file.

**View/Modify Messages-** After successful completion of message generation, the test messages can be viewed or edited. Message Maker provides three views: XML, ER7, and Enhanced ER7. Messages in the Enhanced ER7 view are presented in a tree structure where element values can be modified and saved.

**Message Management-** Message Management provides a utility that allows the user to browse current and previously created messages. It also provides utilities to help organization message test suites (not implemented yet).

## **4 Initialization**

### **4.1 Selecting a Profile**

The Message generation process is driven by a message profile. The profile provides the *template* that guides message creation. To begin the process, select the profile you want to create messages for. The profile can be selected from the Initialization Panel (the default panel upon startup, Figure 2). Click on the “Browse” button to locate a particular profile or enter the path and file name directly in the text field. Once a profile is selected the *session name* and *message path* directory are automatically named. These values are provided for convenience and are suggested values that can be modified. The *session* provides persistence that saves the settings for the message generation process. This

allows for repeating of message generation and partial setup. The *message path* indicates the location where the message files are created and stored.

**Demonstration:** To familiarize yourself with Message Maker’s functionality, you can select the “NIST\_Profile\_DemoL” example provided in the profiles directory as you read through this user’s guide.

## 4.2 Test Options

Message Maker 1.0

File Configure Messages Tools Help

Initialization Data Configuration Message View

**Test Message Set Initialization**

Profile: Documents and Settings\rob\Desktop\Maker Test\NIST\_Profile\_DemoL.xml Browse ... Clear

Session Name: Documents and Settings\rob\Desktop\Maker Test\NIST\_Profile\_DemoL.mmk Browse ... Clear

Message Path: C:\Documents and Settings\rob\Desktop\Maker Test\messages Browse ... Clear

**Test Message Options**

Volume: 20

☐ Create a set of valid test messages ☐ Create a sample message (randomly populated)

☐ Create a set of invalid test messages ☐ Create a sample message (minimally populated)

☐ Create a set of both valid and invalid test messages ☐ Create a sample message (maximally populated)

When generating messages

☒ Ignore length constraints ☐ Enforce length constraints

☒ Customize Settings: More Options >>> ☐ Manual test selection: Set

Figure 2. Initialization Panel

Message Maker supports various message generation options. The options include the number of messages that are created, the message validity, constraints on usage, segment and field cardinality, and more.

### 4.2.1 Predetermined Message Generation Sets

Message Maker by default provides testing variation. When selecting one of the three general test options message variation is provided. You can choose to create messages that are valid, invalid, or a mixture of both. By choosing one of these options, you are allowing Message Maker to control which test options are varied. By default all messages are valid. There are also options to choose a sample message. Sample messages may be minimally populated, maximally populated, or randomly populated. See the glossary for definitions of these terms.

### 4.2.2 Select the Number of Messages to Create

The Volume field allows you to select the number of messages to create. The default number is 20. Volume can be set when the Predetermined Message Generation Sets and Customize Message Creation options are selected.

### 4.2.3 Customize Message Creation

You can have finer control of the testing options by selecting **Customize** and the **More Options** button. This will expand the Initialization Panel (Figure 3). This group of testing options allows you to select the type of messages you want to create.

The screenshot shows the 'Message Maker 1.0' application window. The 'Initialization' tab is selected, and the 'Test Message Set Initialization' section is expanded. It contains three text fields for 'Profile', 'Session Name', and 'Message Path', each with 'Browse...' and 'Clear' buttons. Below this is the 'Test Message Options' section, which includes a 'Volume' field set to 20. There are two columns of radio button options for creating test messages: 'Create a set of valid/invalid test messages' and 'Create a sample message (randomly/minimally/maximally populated)'. A 'When generating messages' section has radio buttons for 'Ignore length constraints' (selected) and 'Enforce length constraints'. The 'Customize Settings' section is active, showing a '<<< More Options' button. Below this are four sub-sections: 'Usage' (Valid selected), 'Coded Entry' (Valid (In code set) selected), 'Cardinality' (Valid (In cardinality range) selected), and 'Length' (Ignore (disregard length attribute) selected). A 'Reset Defaults' button is at the bottom.

Figure 3 Expanded Initialization Panel

The options set by the user in combination with the number of messages to be generated, determine the types (variation) of messages that are generated. The types of messages generated are divided roughly evenly based on which options are selected. For example, if 10 messages are to be generated and *Cardinality* and *Usage* are selected, then 5 messages for testing cardinality and 5 messages for testing usage will be generated.

A base message is a minimally populated message. It serves as the reference message where deviations from it can be identified and recorded as message variants. In selecting the customized options in Figure 3, the user is selecting a given variant or variances, for example, cardinality, from the base message. The “Valid (In cardinality range)” option instructs the message generation engine to create messages that vary the cardinality of segments and fields. The cardinality value and location of the variation from is random. Table 1 gives a summary of options meanings.

Category	Option	Interpretation
Usage	Valid	In the case of RE usage the element is populated with data. The location is random.
Usage	Invalid	An element marked with an X usage may get populated with data or an element with R usage may not get populated with data.
Cardinality	Minimally	All elements with cardinality are set to the minimum.
Cardinality	In range	All elements with cardinality will fall within the cardinality range.
Cardinality	Maximally	All elements with cardinality are set to the maximum.
Cardinality	Invalid	An Element with cardinality will be set to values that fall outside the valid cardinality range.
Code Set	Valid	The value is a valid value taken from the requested code set.
Code Set	Invalid	Not Yet Implemented. When implemented it will be a value not contained in the requested code set.
Length	Valid	All elements have valid lengths.
Length	Ignore	Disregard the length attribute during message creation and validation.
Length	Invalid	Message will contain an element with an invalid length.
<b>Table 1. Meaning of Customized Option Settings.</b>		

The variations in the data used for populating the messages is largely a function of the size of the set of data values available for each primitive element, Field, Component, and Subcomponent. These data values are maintained in a set of XML files that are accessed by the message generation software. The software uses a random number generator to determine the location it will use as its starting point for selecting values from the files. The frequency with which the same location will be selected will then largely be determined by the number of possible values. Subsequent values are selected from the files using a scheme that will increment the starting location by a number that depends on the hierarchical structure of the profile. This scheme should result in relatively little repetition of data values, provided a sufficient number of possible data values are available.

*Cardinality* and *Usage* options result in messages being generated in an analogous manner. The length options work somewhat differently. Length constraints can either be enforced or ignored, but the option's setting doesn't otherwise impact the messages that are generated. When length constraints are being enforced for primitive elements, repeated attempts will be made to find suitable values satisfying the constraint; generally



if such a value is present in the XML data files, it will be used. When the composite length option is set, its only impact is to produce a warning in those cases where a composite element might violate its length constraint, even though none of its component elements violates any length constraint.

When an option for generating a length error is set, a single element in the message will be instantiated with a value that violates the length constraint for some numeric (NM) or string (ST) type only.

#### 4.2.4 Customized Message Creation at the Element Level

Selective element locations and test type can be identified for generating messages. Choose the “Manual Test Selection” button to launch the customized selection panel. This panel depicts the profile in a tree structure and shows the available options that can be selected for generating messages for particular elements. These options vary depending on the validity of the message. By default the options are given for valid messages. Use the drop-down list to change this for invalid or both valid and invalid.




Figure 4. Manual Test Selection Panel

As a reference point, all modifications made to a message variant is made with regards to the base message. The base message is a minimally populated message. See the glossary for a precise definition of both.

Choosing a test category at a selected location indicates to Message Maker that you want to create test messages that vary the constraints at this element. More than one message can be created for a given selection. A running total of message variants are given at the bottom of the panel.

Tables 2 (Valid) and 3 (Invalid) give the interpretation of the options for cardinality as a function of the usage attribute. Table 4 summarizes the options for the usage constraint. Recall that message variants are in reference to the base message, so instances that include the base message settings are not listed here.

Usage	Cardinality	Message Variants
R	1...1	None
R	1...N	3 message variants possible: <ol style="list-style-type: none"> <li>1. Cardinality = 2 (minimum + 1)</li> <li>2. Cardinality = N (if N = * then cardinality is set to the minimum + 3, where 3 is an arbitrary value that can be configured.</li> <li>3. Cardinality = floor (minimum + N)/2. If this value equals one of the values in 1 or 2 above, then only 2 message variants are created in this instance.</li> </ol>
R	M...N	3 message variants possible: <ol style="list-style-type: none"> <li>1. Cardinality = M+1 (minimum + 1)</li> <li>2. Cardinality = N (if N = * then cardinality is set to the minimum + 3, where 3 is an arbitrary value that can be configured.</li> <li>3. Cardinality = floor (M + N)/2. If this value equals one of the values in 1 or 2 above, then only 2 message variants are created in this instance.</li> </ol>
RE	0...1	Cardinality = 1
RE	0...N	3 message variants possible: <ol style="list-style-type: none"> <li>1. Cardinality = 1 (minimum + 1)</li> <li>2. Cardinality = N (if N = * then cardinality is set to the minimum + 3, where 3 is an arbitrary value that can be configured.</li> <li>3. Cardinality = floor (minimum + N)/2. If this value equals one of the values in 1 or 2 above, then only 2 message variants are created in this instance.</li> </ol>
X	Don't care	None

**Table 2. Valid Message Variants for Cardinality**

Usage	Cardinality	Message Variants
R	1...1	Element not included
R	1...N	2 message variants possible: 1. Element not included 2. Cardinality = N + 1 (if N = * then there are no variants)
R	M...N	2 message variants possible: 1. Element not included 2. Cardinality = N + 1 (if N = * then there are no variants)
RE	0...1	None
RE	0...N	Cardinality = N+1 (if N = * then there are no variants)
X	Don't care	Element included
<b>Table 3. Invalid Message Variants for Cardinality</b>		

Validity	Usage	Message Variants
Valid	R	None
Valid	RE	Element included
Valid	X	None
Invalid	R	Element not included
Invalid	RE	None
Invalid	X	Element included
<b>Table 4. Message Variants for Usage</b>		

As an example, consider the selections in Figure 4, where the “Phone Number – Home” component for the “Email address” RE usage attribute is selected. The base message does not populate elements that have a usage of RE, so the selection at this point indicates to the message generator to populate this element. The selection of the cardinality attribute for the “Phone Number – Home” component “[ (999) ] 999-9999 [X99999][C any text]” indicates that messages will be generated that contains 2 and 3 email addresses. The base message covers the case for 1 email address. So a total of 3 message variants are generated for these selections.

#### 4.2.5 Message Generation Characteristics

Each generated message is different in terms of both structure and content. Below is a list of message characteristics that should be considered when choosing options for message generation:

- data content is randomly selected from a database
- at most one variation is introduced for a given message
- at most one error is introduced for a given message

### 4.3 Data File and Configuration

Message Maker provides various ways to input and modify the data that is used in message generation. Configuration, Table, and Reference data can be defined and modified. Configuration data are values that will always be used in a primitive data element. Any item in the reference database can be modified with the use of the “Data

Configuration” panel (including MSH segment and table data). MSH configuration data can be set with the MSH Segment convenience dialog. Table data can be set or modified with the Table Viewer dialog.

### 4.3.1 Data Files

Message Maker maintains a number of XML data files for use in message generation. A brief description for each is given below:

**ConfigData:** This is a special file that contains data items that are always used for an element. Typical *configuration* data might include the HL7 version number or the name of the sending application used in the MSH segment. If a data item is present in this file, the message generation software will use the item’s value when generating messages.


**hl7tables:** This file contains the list of tables defined by HL7. These include HL7 and HL7User table types. The file contains the table id, name, type, and code/value pair. The initial values for the tables are those defined or suggested by the HL7 standard.

**usertables:** This file contains the list of tables defined by HL7 to be of type “User”. There are no suggested values in the standard—the values are site specific (e.g., a hospital room number). These values are typically unique to a particular installation and are defined locally. NIST provides values for these tables (i.e., NIST creates sample values). The NIST created values may be sufficient for many testing scenarios. In such cases where they are not, the tables can be modified with the *Table Viewer*.

**externaltables:** This file contains the list of tables defined by HL7 to be of type “User” with suggested values coming from an external source such as ISO.


**ReferenceData:** The NIST HL7 Reference Database contains example data values for HL7 data elements that are not found in other data sources such as HL7 tables. The database contains items for the HL7 primitive data elements (i.e., field, components, and sub-components). The data items are contained in an Microsoft Access database and are transformed into an XML file for processing by Message Maker.

Together, these data sources are used in the message generation process. Each of the data sources can be modified. When values from a data source are modified, Message Maker will request the name of the file to save (Figure 4) the new data source. By default Message Maker suggests the “Local” prefix. Message Maker will maintain any number of *local* versions of the file.



**Figure 4. Saving Data Files**

The user can select which data files they want to use when generating messages. This can be accomplished with the “**Data Files**” dialog under the “**Configure**” menu (See Figure 5). Once set, the *Local* data files can be used for any message generation session.



**Figure 5. Set Data Files**


Local table data files can be added to the data lookup sequence using the “**Data Files**” dialog. Use the “Load” button to browse the file system to locate the file you want to add. Local table are used when the profile contains references to a local set of table

definitions. [Currently, only one local table can be added. In addition the priority feature that allows the user to set the sequence that the data files are searched is not yet implemented.]

Local table files must adhere to the format that is consistent with the data files provided with Message Maker. At this time, it is the responsibility of the user to provide a local table data file that is compatible. Future versions of Message Maker will provide support for format exported by common tools.

### 4.3.2 MSH Segment Data Initialization

To set configuration data in the MSH Segment, select “MSH Segment” under the “Configure” Menubar. This dialog displays the profile represented as a tree structure. Data items colored in yellow can be modified. Items that are not supported in the profile are colored in gray and contain the text “Not supported by Profile”. Items colored in green, cannot be modified (e.g., the message type MSH.9).



**Figure 6. MSH Segment Initialization**

Items set on this dialog are written to the ConfigData file and as such will be used as the default value in message creation. Change the “Message Control ID” (MSH.10) element to set the beginning sequence number for identifying messages.

### 4.3.3 Table Data Initialization

Tables can be modified, created, or removed using the “**Table Viewer**” dialog (See Figure 7). To create a new table select the “New” button and then provide the Name, Number, Type, and code/value pairs. To remove a table, select the table and click-on the “Remove” button.

Table Viewer

Number: 0001 Type: HL7User Name: Administrative sex Edit Name

New Table Remove Table Cancel

Code	Value
A	Ambiguous
F	Female
M	Male
N	Not applicable
O	Other
S	Special

New Add Remove Edit Cancel

Save Save As ...

Close


**Figure 7. Table Viewer**

When a table is selected, its code/value pairs are shown. Using the utilities provided, the table code/value pairs could be modified. To modify an entry, select the code/value pair of interest. This will copy the entry to the text field provided below. Make the modifications and select the edit button to make the changes permanent. New items can be added to the table by using the “New” and “Add” buttons. Select “New”, enter the code/value pair in the text fields, and select “Add” to include the item into the table. To remove an item, select an entry and click-on the “Remove” button.

### 4.3.4 Data Configuration Panel

The Data Configuration panel is a general-purpose utility that allows the users to modify the data elements in the database, including MSH segment and table data. The Data

Configuration panel allows the user to set various site-specific values that they want to include in messages or allows them to provide customized variation of the data values for particular elements. The view that is presented is a reflection of the profile. All data elements can be modified including table values. The user may add, edit, or delete values from the database. Depending on the type of data value, an appropriate data modification panel on the right side on the Data Configuration panel will appear. To view and/or modify a particular data element browse the tree structure and select the desired element.




**Figure 8. Data Configuration Panel (Table Data Modifications)**

Figure 8 shows modification panel for table data (HL7 Table 0001 Administrative Sex). To add an entry into the table select the New and Add buttons. Select **New**. This activates the two text fields where the *Code* and *Value* pair can be entered. Select the **Add** button to commit the values to the table. To delete an entry from the table, select (highlight) *Code* and *Value* pair and select the **Remove** button. To modify an existing entry select (highlight) the *Code* and *Value* pair. This entry will now appear in the *Code* and *Value* pair text fields below. Perform the modifications and select the **Edit** button to commit the changes to the table.



Data values for primitive elements can also be modified. Figure 9 depicts such a panel. Again use the tree structure to navigate to the element you want to modify. In this case we selected the *PID* segment, the *Patient Name* field and the component *given name*. The component *given name* is highlighted. On the right side of the panel the values in the database for this element are given. You can add, modify, or delete values from this list. Also, for each value you can set the associated attributes (e.g., Complexity). Currently, Message Maker does not yet make use of these attributes; hence changing the attribute values will have no affect on message construction.



**Figure 9. Data Configuration Panel (Reference Data Modification)**

To add an entry into the element list select the **New** and **Add** buttons. Select the **New** button; this activates the text field where a *Value* can be entered. Select the **Add** button to commit the value to the list. To delete an entry from the list, select (highlight) a *Value* and click-on the **Remove** button. To modify an existing entry select (highlight) the *Value*. This entry will now appear in the *Value* text field. Perform the modifications and select the **Edit** button to commit the changes to the list.

## 4.4 Data for Z Segments

Z Segments inherently present a problem for populating message elements with data. We can provide data values for standard HL7 elements because they are known and given in the HL7 database. Z segments contain elements that support their local implementations and therefore have their own nomenclature. There are a number of methods to provide data values for Z –segment elements. A link to a database can be established and the mappings to it can be defined. This would be the optimal solution and will be provided in future versions of Message Maker. A second solution is to map data values provided by the NIST reference database to Z segment elements. The reference database can be search for similar element names where by the user can review to determine if the data maps. If it does, they can choose to copy this data to create a new element field in the reference database (Figure 10). A third method is to use the example data value given in the profile, if one is provided. The fourth method is to use the default values. In this case, if a data value can't be found for a particular message element, then a default data value is assigned based on the data type of the element. Although aesthetically unpleasing, functionally it provides the same utility as data obtained from health care information databases.

Message Maker 1.0

File Configure Messages Tools Help

Initialization Data Configuration Message View

Profile

- MSH
- EVN
- PID
- PV1
- ZEN
  - SET ID - ZEN
  - ENROLLMENT DATE
  - SOURCE OF ENROLLMENT
  - ENROLLMENT STATUS
  - REASON CANCELED/DECLINED
  - CANCELED/DECLINED REMARKS
  - FACILITY RECEIVED
  - PREFERRED FACILITY
  - ENROLLMENT PRIORITY
  - EFFECTIVE DATE
  - ENROLLMENT APPLICATION DATE
  - ENROLLMENT END DATE
  - ENROLLMENT SUB-GROUP

Values

2004  
20040324  
200412

New Add Remove Edit Cancel

Name: ENROLLMENT END DATE

Segment: ZEN

Component:

Subcomponent:

Datatype: DT

Complexity: Typical

Priority: Normal

Category: Valid: Typical

Description:

Save the reference data Save As ...

Suggested Data Link:

End Date


Copy Values

2004  
20040324  
200412

Figure 10. Data Configuration Z-Segments Data Copy

## 5 Message Generation

Once initialization is complete messages can be generated. The minimum initialization requirement is providing a valid message profile. To start the message generator select the “*Generate...*” item under the “*Messages*” menu. This will launch the Generate Messages Dialog, See Figure 11. Click-on the **Start** button to begin the process.



**Figure 11. Generate Message Dialog**

Upon completion messages are saved in the “Message Path” directory specified during initialization. The messages are stored as XML files. Internally, Message Maker processes messages as XML representations. Messages can be saved in XML or ER7 format. To save messages select the Save item from the Messages menu. If you wish to subsequently edit messages, the XML version must be saved. Messages that are not explicitly saved will be removed when Message Maker exits. Messages can be deleted by selecting the Delete item from the Messages menu.

### 5.1 How Message Elements are Populated with Data

Message Maker has a defined sequence when populating primitive message elements with data. The precedence order is given below:

1. Values predetermine by the HL7 specification and present in the profile, for example, MSH.9, the Message Type.
2. Constant Values defined in the profile (ConstantValue attribute)
3. Configuration Values set by the user either through the MSH Segment configuration panel or the Data Configuration panel. Data that is explicitly saved as configuration data. The “namespace ID” for the “Sending Application, MSH.3, is a typical example. Here, the user wants to set this value so that it appears in every message with the same value.
4. If an element defines a Table, the data is random selected from the table. Tables are search by default in the following order:
  - a. HL7 Tables
  - b. User Tables
  - c. External Tables
  - d. Local TablesThe priority of how tables are searched can be set using the “Data Files” dialog’s “Set Priority” utility (not yet implemented). Local Tables are tables provided by the user and imported into Message Maker.
5. Reference Database
6. Example value given in the profile

7. Default Values. These values are chosen based on the data type of the primitive element. For example, an element with a data type of string (ST) is set to “”.





Figure 12. Message View Panel (XML View)

## 6 Message Browsing and Editing

Select the Message View tab to review and edit the messages. The Message Path directory selected during initialization is automatically mounted. Open this folder and select the metadata file associated with your message test suite. By default the name of this file is the name of the profile with a “MD\_” prefix. Selecting this file gives a summary of the messages in the display panel on the right.

Opening the metadata folder displays the list of messages. By default the name of the message files are the profile name with a “.msg00000.xml”, where the “00000” represents the message sequence number. By default it starts as 0. Select a message to view its contents. Messages can be rendered in XML, ER7, or Enhanced ER7 formats. By default messages are displayed in XML (Figure 12). Select the ER7 tab at the bottom to display the message in the ER7 format. Select Enhanced ER7 to view and navigate messages in a tree-structure. The Enhanced ER7 view also allows the user to edit the

content of the data values in the message. To change the value of a data element, select the value, make the changes, and hit enter (Figure 13).



**Figure 13. Message View Panel (Enhanced ER7 View-Edit)**

Modifications made to messages can be saved. Messages saved with the same name will still be associated with the originating metadata file. Messages saved under a different name will not be associated with a metadata file.

## 6.1 Viewing Previously Generated Messages

Messages that were previously generated can be view by mounting the directory where the messages were saved. Choose the Mount Directory dialog from the Messages menu.

## 7 Appendix A: Message Maker Version 1.0 Limitations

The following list gives the current known limitations of this version of Message Maker. Future versions of Message Maker will include this functionality.

1. The reference data is limited to version 2.4 elements.
2. Localization (Z-segments) is not handled. Although, the Message Generator should process the segments correctly, there is no support to populate their data

- elements them with values (i.e., values don't exist). Update: Version 1.1 supports Z-Segments to a certain extent. Z-segments are expressed in the ER7 encoding.
3. Only ADT messages are supported. Although, any message type can be process, the reference data is populated mostly for ADT data elements. Update: Version 1.1 provides default values for all data types. Therefore messages will be populated with data values.
  4. The reference data is not yet fully populated. It is partially populated for ADT message types.
  5. Message Maker is has limited facilities for importing site-specific data.
  6. Message Maker has limited validation and reporting functionality. Messages can be invalid.
  7. There is no support for the C and CE usage types.
  8. Not all data types are handled (e.g., the HD data type).

## 8 Appendix B: Trouble Shooting

### 1. Profile fails to load.

Check to see if the profile is a valid XML file. In some cases the XML files created by profile generation tools, such as the MWB, contained illegal characters. Try and view the profile with Internet Explorer.

## 9 Glossary

**Base message.** A base message is a minimally populated message. It serves as the reference message where deviations from it can be identified and recorded as message variants.

**Maximally populated message.** A maximally populated message will follow the usage rules at each level as stated. In the case of an RE the element will be populated. For cardinality, all maximums are selected. In cases where the maximum is unbounded, the maximum is set to the minimum + 3. All lengths fall within the specified limits at each level. If the option to ignore lengths is chosen then the length constraint attribute is eliminated. All coded values are taken from the specified value set.

**Minimally populated message.** A minimally populated message will follow the usage rules at each level as stated (e.g., in the case of R usage, the element is populated). In the case of an RE the element will not be populated. For cardinality, all minimums are selected. All lengths fall within the specified limits at each level. If the option to ignore lengths is chosen then the length constraint attribute is eliminated. All coded values are taken from the specified value set.

**Sample message.** A sample message will follow the usage rules at each level as stated. In the case of an RE the element is randomly populated. For cardinality, a value within the specified limits including the edges is randomly selected. All lengths fall within the

specified limits at each level. If the option to ignore lengths is chosen then the length constraint attribute is eliminated. All coded values are taken from the specified value set.